Procedure Activations

Lifetime of procedure:

- Begins when control enters activation (call)
- Ends when control returns from activation

Activation Tree:

- Shows flow of control from one activation to another
- Root: Main program
- Edges: Call from one procedure to another (read left to right)
- <u>Leaves</u>: Procedures that call no other procedures

Example

```
main
  procedure P
  begin
    procedure S begin ... end S;
  if random(1) < 1 then P()
    else { S(); Q() }
  end P;
  procedure Q begin ... end Q;
  P;
  Q;
  P;</pre>
```

27

Sample Activation Trees

Activation Trees and Stack Frames

Running a program corresponds to a **traversal** of (one of) its activation tree(s).

We can represent the traversal of the tree using a **stack**.

Each item on the stack is called a frame.

⇒ The stack of frames not only maintains the call sequence info, but also keeps track of the local and non-local environment for each procedure.

28

Content of Stack Frames

- Run-time stack contains frames for main program and each active procedure.
- Each stack frame includes:
- Pointer to stack frame of caller (Control Link)
- 2. Return address (within caller)
- Mechanism to find non-local variables (Access Link)
- 4. Storage for parameters
- 5. Storage for local variables
- 6. Storage for temporary and final values
- In a language with first-class functions, this is more complex.

Procedure Activation and Run-time Stack

On a call:

end

26

- Set up stack frame on top of run-time stack (current context)
- 2. Do the real work of the procedure body
- Release stack frame and restore caller's context (as new top of stack)

Run-time stack establishes a **context** for a procedure invocation

Context of Procedures

Two contexts:

- static placement in source code (same for each invocation)
- dynamic run-time stack context (different for each invocation)

Name Resolution: Given the use of a name (variable or procedure name), which instance of the entity with that name is referred to?

 \Rightarrow Both static and dynamic contexts play a role in this determination.

Scope

Each use of a name must be associated with a single entity at run-time (ie, an offset within a stack frame).

The **scope** of a declaration of a name is the part of the program in which a use of that name refers to that declaration.

The design of a language includes **scope rules** for resolving the mapping from the use of each name to its appropriate declaration.

Some Terminology

A name is:

- visible to a piece of code if its scope includes that piece of code.
- local to a piece of code (block/ procedure/main program) if its declaration is within that piece of code.
- non-local to a piece of code if it is visible, but its declaration is not within that piece of code.

A declaration of a name is **hidden** if another declaration supersedes it in scope.

Scope Rules

Two choices:

- 1. Use static context: **lexical scope**
- 2. Use dynamic context: dynamic scope

For local names, these are the same.

⇒ Harder for non-local names, and not necessarily the same for both types of scope.

Scope Example

```
program L;
   var n: char:
                   {n declared in L}
   procedure W;
   begin
    write(n);
                   {n referenced in W}
   end;
   procedure D;
      var n: char; {n declared in D}
   begin
      n:= 'D':
                   {n referenced in D}
   end;
begin
 n:= 'L';
                   {n referenced in L}
 W;
```

Lexical Scope

- Names are associated with declarations at compile time
- Find the smallest block syntactically enclosing the reference and containing a declaration of the name
- Example:

36

- The reference to n in W is associated with the declaration of n in L
- The output is?

Benefit: Easy to determine the right declaration for a name from the text of the program.

37

38

34

35

end.

Dynamic Scope: Pros and Cons

Benefit: reduces need for parameters.

Problems:

- hard to understand behavior from the text alone.
- renaming variables can have unexpected results.
- no protection of one's local variables from a called procedure.
 (Ie, if A calls B, B can modify A's local variables.)
- can be slower to execute.

NOTE: Most languages use lexical scope, although early interpreted languages used dynamic scope because of the flexibility and ease of implementation.

Scoping and the Run-time Stack

Access link shows where to look for non-local names.

Static Scope:

Access link points to stack frame of the lexically enclosing procedure (total no. links to follow determined at compile time)

Dynamic Scope:

Access link points to stack frame of caller

Nested Procedures and Static Scope

rogram	
a,b,c : integer;	// 1
procedure r	
a : integer;	// 5
a b c	
end r;	// 6
procedure p	
c : integer;	// 3
procedure s	
d,e : integer	// 8
a b c	
r;	// 9
end s;	
r;	// 4
s;	// 7
end p;	
p;	// 2
nd	

Example:

at run time

 The reference to n in W is associated with two different declarations at two different times

Dynamic Scope

Names are associated with declarations

Find the most recent, currently active

run-time stack frame containing a

declaration of the name

- The output is?

39 40

Nesting Depth and Access Links

procedure v

...u...; /* use of u */

begin /* v */

end; /* v */

Main program has nesting depth 1.

42

46

• Body of p has nesting depth 2.

lexical levels deep it is.

• Body of s has nesting depth 3.

Note: Declarations of p and r have nesting depth 1, but declarations and statements within p and r have nesting depth 2.

Nesting Depth

Nesting depth of a procedure is how many

To determine the access link for name u, follow n-m access links from proc v in which u is used, where n is the nesting depth of the body of ${\tt v}$ and m is the nesting depth of the declaration of u.

Run-Time Stack Trace

Trace through above program, showing snapshot of run-time stack at points 1, 3, 5, 8, 5 (again).

Dynamic Scope Example

program a : integer; procedure z a : integer; ... a := 1; у; output a; end z; procedure w a : integer; ... a := 2: output a; end w; procedure y ... a := 0; end y; a := 5; z; w; output a; end

44

Optimizing Variable Access

Problem: Accessing non-local names requires following links up the access link chain.

Solution for lexical scoping only:

static-chain frames.

- Called the display
- Pioneered in Algol60
- Makes addresses directly accessible

Using a Display

- find variable addresses
- frames
- A variable is stored at an offset in the frame pointed to by the i'th display
- Display must be maintained along with

Display in Static Example

For example, during execution of proc s:

D[1]: Pointer to stack frame for main pgm

D[2]: Pointer to stack frame for procedure p

D[3]: Pointer to stack frame for procedure s

- Address of d is D[3]+Offset+0
- Address of e is D[3]+Offset+1
- Address of c is D[2]+Offset+0
- Address of a is D[1]+Offset+0
- Address of b is D[1]+Offset+1

Maintaining the Display

45

49

48

Maintain a vector of currently-active

43

47

\bullet If a procedure is at nesting depth n, it may have to follow n-1 static links to

• Display is an array of pointers to stack

element, where i is the nesting level of procedure where variable was declared

run-time stack

Summary:

Procedural Language Design Issues

- Components of a procedure
- name
- parameters
- body
- optional result
- Parameter passing
- pass by value
- pass by result
- pass by value-result
- pass by reference
- pass by name
- Aliasing through parameter passing
- Procedure Activations
- Stack frames
- Lexical scope
- Dynamic scope
- Implementing scope with stack frames
- Displays